

Maxwell Service

Install

```
# yum install -y hubzero-mw-service
```

Configure

```
# mkvztemplate amd64 squeeze shira
```

```
# hzcms configure mw-service --enable
```

Test

```
# maxwell_service startvnc 1 800x600 24
```

Enter an 8 character password when prompted (e.g., "testtest")

This should result in a newly create OpenVZ session with an instance of a VNC server running inside of it. The output of the above command should look something like:

```
Reading passphrase:
```

```
testtest
```

```
===== begin /etc/vz/conf/hub-  
session-5.0-amd64.umount =====
```

```
Removing /var/lib/vz/root/1 :root etc var tmp dev/shm dev
```

```
===== end /etc/vz/conf/hub-  
session-5.0-amd64.umount =====
```

```
stunnel already running
```

```
Starting VE ...
```

```
===== begin /etc/vz/conf/1.mount =====  
=====
```

```
Removing and repopulating: root etc var tmp dev
```

```
Mounting: /var/lib/vz/template/debian-5.0-amd64-maxwell home apps
```

MAXWELL SERVICE

```
===== end /etc/vz/conf/1.mount =====
=====
VE is mounted
Setting CPU units: 1000
Configure meminfo: 2000000
VE start in progress...
TIME: 0 seconds.
Waiting for container to finish booting.
/usr/lib/mw/startxvnc: Becoming nobody.
/usr/lib/mw/startxvnc: Waiting for 8-byte vncpasswd and EOF.
1+0 records in
1+0 records out
8 bytes (8 B) copied, 3.5333e-05 s, 226 kB/s
Got the vncpasswd
Adding auth for 10.51.0.1:0 and 10.51.0.1/unix:0
xauth:  creating new authority file Xauthority-10.51.0.1:0
Adding IP address(es): 10.51.0.1
if-up.d/mountnfs[venet0]: waiting for interface venet0:0 before doing
NFS mounts (warning).
WARNING: Settings were not saved and will be resetted to original values
on next start (use --save flag)
```

```
# vzlist
      VEID      NPROC STATUS  IP_ADDR      HOSTNAME
      1          6 running 10.51.0.1    -
```

```
# openssl s_client -connect localhost:4001
```

This should report an SSL connection with a self signed certificate and output text should end with:

```
---
RFB 003.008
```

If you see this then you successfully connected to the VNC server running inside the newly created OpenVZ session.

Clean up

```
# maxwell_service stopvnc 1
```

Which should give output similar to:

```
Killing 6 processes in veid 1 with signal 1
Killing 7 processes in veid 1 with signal 2
Killing 5 processes in veid 1 with signal 15
Got signal 9
Stopping VE ...
VE was stopped
===== begin /etc/vz/conf/1.umount =====
=====
Unmounting /var/lib/vz/root/1/usr
Unmounting /var/lib/vz/root/1/home
Unmounting /var/lib/vz/root/1/apps
Unmounting /var/lib/vz/root/1/.root

Removing /var/lib/vz/root/1 :root etc var tmp dev/shm dev
Removing /var/lib/vz/private/1: apps bin emul home lib lib32 lib64 mnt
  opt proc sbin sys usr .root
===== end /etc/vz/conf/1.umount =====
=====
VE is unmounted
```